



Sage 100 Contractor 2014 (formerly Sage Master Builder)

Installation and License Administration Guide

United States Edition

Version 19.6

**This version of the software
has been retired**

This is a publication of Sage Software, Inc.

Copyright © 2015. Sage Software, Inc. All rights reserved.

Sage, the Sage logos, and the Sage product and service names mentioned herein are registered trademarks or trademarks of Sage Software, Inc. or its affiliated entities. All other trademarks are the property of their respective owners.

Microsoft ®SQL Server®, Windows Vista® and the Windows logo are either registered trademarks or trademarks of Microsoft Corporation in the United States and/or in other countries.

Your use of this document and the Sage product(s) described herein is governed by the terms and conditions of the Sage End User License Agreement ("EULA") or other agreement that is provided with or included in the Sage product. Nothing in this document supplements, modifies or amends those terms and conditions. Except as expressly stated in those terms and conditions, the information in this document is provided by Sage "AS IS" and Sage disclaims all express, implied or statutory warranties of any kind, including but not limited to the warranties of merchantability, fitness for a particular purpose or of non-infringement. No implied license is granted to you under any Sage intellectual property or trade secret right. Sage reserves the right to revise, supplement or remove information in this document at any time without notice to you or others.

Sage End User License: <http://na.sage.com/sage-na/eula>

Last updated: November 12, 2015

Contents

- Chapter 1: Welcome to Sage 100 Contractor Installation 1**
 - How to read this document 1
 - Customer Support and resources 2
 - Training resources 4
 - Business partners 5
 - The Users Group 5
 - Business forms 5

- Chapter 2: System Configuration 7**
 - Internet access required for Sage 100 Contractor 7
 - Network configuration and licensing 7
 - Windows permissions required for Sage 100 Contractor 11
 - Report scheduling and faxing functionality 13

- Chapter 3: Sage 100 Contractor Installation 17**
 - Installation preview 17
 - New installations 20
 - Upgrade installations 23
 - Uninstalling Sage 100 Contractor from a Sage license server 25

- Chapter 4: ACT! Plug-in Installation 27**
 - Pre-installation information 27
 - Duration of the installation process 27
 - Additional required software 27
 - Installing the ACT! Plug-in 27

- Chapter 5: Sage Construction Anywhere Installation 29**
 - Additional required software 29
 - Duration of the installation process 29
 - Pre-installation information 29
 - Setting up Sage Construction Anywhere Integration 30
 - Setting up an API security group and an API user in Sage 100 Contractor 30

Chapter 6: Managing Your License	33
License administration	33
Chapter 7: License Use and Sage 100 Contractor	35
Specify Sage License Server	35
Chapter 8: Special Configurations—Operating Systems and Services	37
Windows 8 Professional and Server 2012 Standard Operating Systems	37
Windows 7 Professional and Server 2008 R2 Standard Operating Systems	38
Windows Vista and Server 2008 Operating Systems	40
Citrix and Terminal Servers	41
Backing Up Your Data	42
Configuring Windows Regional and Short Date Format	44
Index	45

Chapter 1: Welcome to Sage 100 Contractor Installation

Welcome to Sage 100 Contractor installation. Sage 100 Contractor can run in many different software and network environments, with implications you need to consider as you prepare to install the software. The more you understand about the installation process and how it relates to your software and network environment, the more likely your installation will proceed smoothly.

This chapter provides more information about customer resources, such as:

- Other printed and printable guides
- The user-assistance Help system
- Contacts for Customer Support
- Sage 100 Contractor training
- Information about business partners.

How to read this document

This document uses the following conventions:

- The names of screens, windows, fields, and other features displayed by the software are shown in **bold type**.
- Information you enter into the software is in bold type, as in the following example:
Enter **Miscellaneous** in the **Amount Type** box.
- Names of keys are shown in capitals; for example, ENTER, TAB. A plus sign (+) between two key names indicates that you should press both keys at the same time; for example, SHIFT + TAB.
- The names of buttons you can click with your mouse are enclosed in bold type; for example, [**OK**] and [**Post**].



TIP: This symbol draws your attention to helpful information to make it easier for you to use Sage 100 Contractor.



NOTE: This symbol draws your attention to information of particular interest, such as information not included in steps.



CAUTION: This symbol draws your attention to information that is important because it can help you avoid a costly or time-consuming error.



IMPORTANT: This symbol draws your attention to information that is of critical importance.

Customer Support and resources



IMPORTANT: Before you contact the Customer Support Call Center, take advantage of the following resources, which are available 24 hours a day, 7 days a week.

Sage 100 Contractor Help

From anywhere in the Sage 100 Contractor software, you can display this comprehensive library of accessible topics to learn more about specific procedures, topics, fields, or buttons.

Product documentation

The software comes with several PDF guides, including *Release Notes*, *Installation and License Administration Guide*, and *User Guide*, among others.

To view the guides, click **Home & Resources tab > Product Documentation** or, if you have Activity Centers hidden, click **Resources > Printable Documentation**.

Sage Knowledgebase

Depending on your Sage service plan, we offer a web-based Sage Knowledgebase and online user community forums at www.na.sage.com or through the in-product menu. Our staff maintains an extensive knowledge database of questions and answers covering everything from frequently asked questions to more complex problems and solutions. In addition, we keep all product reference documentation available in the Knowledgebase. This online tool is the same tool we use in our customer support call center to help answer your call.

To log in to the Sage Knowledgebase:

1. Go to <https://support.na.sage.com/>.
2. In the upper-right section of the page, above the Search, click **Login**.
3. Enter your Customer Portal **Username** and **Password**.
4. Click **Log on**.

Contacting Customer Support

Depending on your Sage service plan, you may be able to contact the Sage Customer Support Call Center to work with one of our highly trained customer support professionals. The Knowledgebase article [How do I get technical support for Sage 100 Contractor?](#) provides contact information and hours of operation, and it can help you to determine which service works best for you.

Our analysts work with you to respond accordingly to the urgency of your issue.

Call urgency can range from a simple explanation of software settings to critical situations in which work is stopped or data integrity is compromised. Some calls may warrant further research and followup, in which

case our support analyst will place your call in his/her in-progress work list. At every step of the way, we work with you until we reach a resolution or agreement.

Depending on your Sage service plan, you may check the status or update, or even create a new support ticket online:

1. Visit www.na.sage.com.
2. In the upper-right section of the page, above the Search, click **Login**.
3. Enter your Customer Portal **Username** and **Password**.
4. Click **Log on**.
5. On the right, select **Submit a customer support case**.

Before you call customer support

Be sure to have the following information on hand so we can handle your call efficiently.

Question	How to Find the Answer
What is your Sage client ID number?	Your client ID number can be found on correspondence you receive from Sage. If you do not know your Sage client ID, contact the person at your company who maintains your relationship with Sage.
What software version are you using?	To find the version, open Sage 100 Contractor; click Help > About Sage 100 Contractor and note the number listed.
What application or area in the software are you calling about?	On the menu list, identify the application and window where are you are working (i.e. Selecting Invoices to Pay in 4-3-1, Accounts Payable Vendor Payments).
How can we help you?	Walk through the exact steps you completed with as much detail and accuracy as possible.
Is there an error message?	Write down the exact wording of the message.
Can you reproduce the issue?	Were you able to walk through the same steps that led to the problem and see whether it happened again?
Is this the first time the problem has happened? Does the problem occur on one workstation or several?	Ask other users if they have experienced the same problem. Have them test at their workstation to see if they experience the same problem. Also, have the original user try other workstations to see whether the problem is specific to that user.

Question	How to Find the Answer
Has anything changed with your software, hardware, or workflow?	Ask your network administrator for technical information regarding anything that may have changed behind the scenes: upgrades to Sage 100 Contractor, new third-party software installations, moving of data from one server to another, new printers or print driver installation, or anything else that might affect the network.
Does the problem happen in the sample data sets?	Select [File> Open Company] , then change the drive letter on the dropdown to C:, select Sample Company.
What kind of network are you using?	If you do not know, contact your network administrator.
What operating system is on your computer?	For Vista: Click [Start] , type winver in the 'start search' window and click [OK] .
What printers and print drivers are installed?	If you do not know, contact your network administrator.
When was your last backup?	If you do not know, contact your network administrator.

Training resources

When you choose to take online classes from Sage or work with a Sage business partner, you will learn how to use Sage 100 Contractor to support your business. Contact your business partner to find out about training options or visit Sage University at <http://www.sageu.com>.

Online classes

Online classes help you maximize your use of Sage 100 Contractor. Online classes are a convenient training option for your company and new users to learn more about Sage 100 Contractor so you can get the most out of the software. You can select from classes on all aspects of Sage 100 Contractor, including project management, estimating, scheduling, service management and payroll. Each online class is led by an instructor with years of experience using Sage 100 Contractor. During the class, you will be able to follow along as the instructor demonstrates functions and workflows in Sage 100 Contractor. In the online live session, you can ask questions and benefit from hearing answers to other students' questions.

For more information, visit <http://www.sageu.com>.

Getting started as a new user

We recommend that all new users should begin with our New Customer Training (NCT) series, which is included in our Essentials Training Package in recorded format for 24/7 access. If you prefer live online training led by an instructor, you can register for the Realtime Learning version of these NCT courses. For more information, visit <http://www.sageu.com>.

Business partners

To serve you better, Sage 100 Contractor products and services are available to you through an authorized network of business partners. Business partners have local expertise and regional knowledge working with contractors in the region.

Your business partner is available to serve you, from simple how-to questions and hands-on demonstrations, to installation, implementation, and training. They're fully equipped to help you get where you want to be. For more information, contact your Sage 100 Contractor business partner.

The Users Group

TUG, The Users Group for Sage 300 Construction and Real Estate, Sage 100 Contractor, and Sage Estimating is a not-for-profit, professional organization committed to supporting the users of Sage 100 Contractor and other Sage construction software.

You can find out more about the group, their services, and how to become a member at <http://tugweb.site-ym.com/default.asp?>.

Business forms

Sage 100 Contractor is designed to work with generic checks and forms that are available from many sources. There is no single vendor that customers must use; however, you can get a complete portfolio of forms, tax forms, and checks through *Sage Construction and Real Estate Forms* by calling 800-760-7929 or by visiting www.sagecreforms.biz.

Chapter 2: System Configuration

This chapter presents technical information about how to configure Sage 100 Contractor for specific operating systems.

For current information about supported operating systems, Internet browsers, and other software, and about system requirements for servers and client workstations, refer to our Knowledgebase article ID 62172, available at <https://support.na.sage.com/selfservice/viewdocument.do?externalId=62172>.

Make sure your computers meet the system requirements before you install the software. Sage 100 Contractor may not run properly or at all on computers that do not meet the minimum requirements.

Internet access required for Sage 100 Contractor

Sage 100 Contractor features, such as printing or e-filing tax forms, submitting enhancement requests, accessing Help, or downloading periodic product or tax updates all require Internet access.

To take advantage of these features, ensure that any workstation or server that Sage 100 Contractor is installed on has access to the Internet.

During installation of Sage 100 Contractor, the computer serving as the Sage license server must be able to connect to the Internet to obtain licenses. Once installation is complete, you can check out license uses for each computer where Sage 100 Contractor is installed, then disconnect the Sage license server from the Internet.



NOTE: A static Internet connection using a compatible web browser is required for Sage Construction Anywhere. For current information on supported browsers, supported Sage 100 Contractor versions, and other system requirements, see the Sage Construction Anywhere help at http://help.sageconstructionanywhere.com/sage100contractor/help/Default.htm#01_Setup/System_requirements.htm.

Network configuration and licensing

About network configuration and TCP Remoting Channel

Sage 100 Contractor uses the TCP Remoting Channel, a Microsoft .NET Framework component, to enable communication among computers on a network. By default, Sage 100 Contractor uses the TCP starting port 48750. Certain configurations can potentially disable the communication:

- File sharing on computers running the Windows 8, Windows 7, Vista, Server 2008, Server 2008 R2, and Server 2012 operating system must be enabled. To enable file sharing, follow the instructions in the Windows Help.
- TCP communication requires the selection of port numbers that are not in use by other processes on the local computer.
- Software firewalls running on the local computer can be configured to block processes from opening TCP ports, which will prevent communication through the TCP Remoting Channel.

Configuring Sage 100 Contractor Hosting Framework TCP port number

Sage 100 Contractor uses the TCP starting port number 48750 as the default. You can configure the port number using the XML file Sage.CRE.HostingFramework.Service-InstanceConfig.xml, located in the **Programs (x86)\Sage\Sage 100 Contractor** folder.

If you need to change the default port numbers for the Sage 100 Contractor Hosting Framework using the Sage.CRE.HostingFramework.Service-InstanceConfig.xml file, you must change it on every computer on the network where Sage 100 Contractor is installed. In addition, after making this change, the Sage 100 Contractor Hosting Framework on each computer running Sage 100 Contractor must be restarted.



NOTE: Consult your IT administrator for alternative port numbers.

To change the port numbers:

1. In Window Explorer, locate Sage.CRE.HostingFramework.Service-InstanceConfig.xml in the path Programs(x86)\Sage\Sage 100 Contractor.
2. Right-click Sage.CRE.HostingFramework.Service-InstanceConfig.xml, then open it with a text editor, such as Notepad.
3. Near the end of the file, between the **<StartingPort>** **</StartingPort>** tags, locate the port number.
4. Change the port number.
5. Save, and then close the file.

Repeat these steps on every computer running Sage 100 Contractor.

Configuring anti-virus software and third-party firewalls

During installation of the Sage 100 Contractor Hosting Framework, the Windows Firewall is configured automatically to allow the Sage 100 Contractor Hosting Framework to act as a TCP server. If you use some other firewall, however, you may need to manually adjust some settings in the firewall in order to ensure proper operation.

You can use the following basic procedure to manually configure the Windows Firewall to allow the Sage 100 Contractor Hosting Framework to communicate with other computers. Use it as the basis for manually configuring other third-party firewall products.

To configure the Windows Firewall:

1. For Windows Vista or Server 2008, click **Start > Control Panel > Security**.
For Windows 7, click **Start > Control Panel > System and Security**
For Windows 8, click **Start > All apps > Control Panel > System and Security**.
2. Open **Windows Firewall**, and then select **Allow a program or feature through Windows Firewall**.
3. If Sage 100 Contractor Hosting Framework is not on the list, you can add it by selecting **Add Program**, then browsing to the following path:
\\MB7\Programs\Sage.CRE.HostingFramework.Service-InstanceConfig.xml.



NOTE: By default, the exception is set to allow access by any computer on the network. You can refine this setting by selecting the **Change Scope** button. Be aware that restricting the scope incorrectly can cause the computer to be unable to connect with some or all of the other machines on the network.

Files to exclude when manually configuring your firewall for Windows 8 Professional 32-bit

- C:\MB7
- C:\ProgramData\Sage\Sage 100 Contractor
- C:\Program Files\Sage\Sage 100 Contractor
- C:\ProgramData\Aatrix Software
- C:\Program Files\Aatrix Software
- C:\%LocalAppData%\Sage\Sage 100 Contractor
- Network location of Sage 100 Contractor data

Files to exclude when manually configuring your firewall for Windows 8 Professional 64-bit

- C:\MB7
- C:\ProgramData\Sage\Sage 100 Contractor
- C:\Program Files (x86)\Sage\Sage 100 Contractor
- C:\Program Files (x86)\Aatrix Software
- C:\ProgramData\Aatrix Software
- C:\%LocalAppData%\Sage\Sage 100 Contractor
- Network location of Sage 100 Contractor data

Files to exclude when manually configuring your firewall for Windows Vista 32-bit

- C:\MB7
- C:\ProgramData\Sage\Sage 100 Contractor
- C:\Program Files\Sage\Sage 100 Contractor
- C:\ProgramData\Aatrix Software
- C:\Program Files\Aatrix Software
- C:\%LocalAppData%\Sage\Sage 100 Contractor
- Network location of Sage 100 Contractor data

Files to exclude when manually configuring your firewall for Windows Vista 64-bit

- C:\MB7
- C:\ProgramData\Sage\Sage 100 Contractor
- C:\Program Files (x86)\Sage\Sage 100 Contractor

- C:\Program Files (x86)\Aatrix Software
- C:\ProgramData\Aatrix Software
- C:\%LocalAppData%\Sage\Sage 100 Contractor
- Network location of Sage 100 Contractor data

Files to exclude when manually configuring your firewall for Windows 7 Professional 32-bit

- C:\MB7
- C:\ProgramData\Sage\Sage 100 Contractor
- C:\Program Files\Sage\Sage 100 Contractor
- C:\ProgramData\Aatrix Software
- C:\Program Files\Aatrix Software
- C:\%LocalAppData%\Sage\Sage 100 Contractor
- Network location of Sage 100 Contractor data

Files to exclude when manually configuring your firewall for Windows 7 Professional 64-bit

- C:\MB7
- C:\ProgramData\Sage\Sage 100 Contractor
- C:\Program Files (x86)\Sage\Sage 100 Contractor
- C:\Program Files (x86)\Aatrix Software
- C:\ProgramData\Aatrix Software
- C:\%LocalAppData%\Sage\Sage 100 Contractor
- Network location of Sage 100 Contractor data

Files to exclude when manually configuring your firewall for Windows 8 Professional

- C:\MB7
- C:\ProgramData\Sage\Sage 100 Contractor
- C:\Program Files (x86)\Sage\Sage 100 Contractor
- C:\Program Files (x86)\Aatrix Software
- C:\ProgramData\Aatrix Software
- C:\%LocalAppData%\Sage\Sage 100 Contractor
- Network location of Sage 100 Contractor data

Files to exclude when manually configuring your firewall for Windows Server 2008, 2011, 2012

- C:\MB7

- C:\ProgramData\Sage\Sage 100 Contractor
- C:\ProgramFiles (x86)\Sage\Sage 100 Contractor
- C:\Program Files (x86)\Aatrix Software
- C:\ProgramData\Aatrix Software
- C:\%LocalAppData%\Sage\Sage 100 Contractor
- Network location of Sage 100 Contractor data

Windows permissions required for Sage 100 Contractor

When you install Sage 100 Contractor, work with your system administrator to configure the Windows-level security that corresponds to the operating system installed on each workstation where Sage 100 Contractor will be used. Without the correct permissions, users may have difficulty operating Sage 100 Contractor.



CAUTION: Always back up your data before changing Windows permissions! Setting Windows security incorrectly can adversely affect system operations. Sage is not responsible for problems caused by incorrectly configured Windows settings.

All the directories listed below must have **Full Control, Modify, Read & execute, List folder contents, Read,** and **Write** permission. **Special permissions** are not required.

Permissions required

Windows component/ version	Directories
Registry Keys	HKEY_Current_User\Software\Sage HKEY_Local_Machine\Software\Wow6432node\Sage HKEY_Current Config\Software\Sage 100 Contractor PDF Export HKEY_Current Config\Software\Sage 100 Contractor RTF Export
Windows 8 Professional 32-bit	C:\MB7 C:\ProgramData\Sage\Sage 100 Contractor C:\Program Files\Sage\Sage 100 Contractor C:\ProgramData\Aatrix Software C:\Program Files\Aatrix Software C:\%LocalAppData%\Sage\Sage 100 Contractor Network location of Sage 100 Contractor data
Windows 8 Professional 64-bit	C:\MB7

Windows component/ version	Directories
	<p>C:\ProgramData\Sage\Sage 100 Contractor</p> <p>C:\Program Files (x86)\Sage\Sage 100 Contractor</p> <p>C:\Program Files (x86)\Aatrix Software</p> <p>C:\ProgramData\Aatrix Software</p> <p>C:\%LocalAppData%\Sage\Sage 100 Contractor</p> <p>Network location of Sage 100 Contractor data</p>
Windows 7 Professional 32-bit	<p>C:\MB7</p> <p>C:\ProgramData\Sage\Sage 100 Contractor</p> <p>C:\Program Files\Sage\Sage 100 Contractor</p> <p>C:\ProgramData\Aatrix Software</p> <p>C:\Program Files\Aatrix Software</p> <p>C:\%LocalAppData%\Sage\Sage 100 Contractor</p> <p>Network location of Sage 100 Contractor data</p>
Windows 7 Professional 64-bit	<p>C:\MB7 C:\ProgramData\Sage\Sage 100 Contractor</p> <p>C:\Program Files (x86)\Sage\Sage 100 Contractor</p> <p>C:\Program Files (x86)\Aatrix Software</p> <p>C:\ProgramData\Aatrix Software</p> <p>C:\%LocalAppData%\Sage\Sage 100 Contractor</p> <p>Network location of Sage 100 Contractor data</p>
Windows Server 2008, 2011, 2012	<p>C:\MB7</p> <p>C:\ProgramData\Sage\Sage 100 Contractor</p> <p>C:\ProgramFiles (x86)\Sage\Sage 100 Contractor</p> <p>C:\Program Files (x86)\Aatrix Software</p> <p>C:\ProgramData\Aatrix Software</p> <p>C:\%LocalAppData%\Sage\Sage 100 Contractor</p> <p>Network location of Sage 100 Contractor data</p>

Windows component/ version	Directories
Windows Vista 32-bit	C:\MB7 C:\ProgramData\Sage\Sage 100 Contractor C:\Program Files\Sage\Sage 100 Contractor C:\ProgramData\Aatrix Software C:\Program Files\Aatrix Software C:\%LocalAppData%\Sage\Sage 100 Contractor Network location of Sage 100 Contractor data
Windows Vista 64-bit	C:\MB7 C:\ProgramData\Sage\Sage 100 Contractor C:\Program Files (x86)\Sage\Sage 100 Contractor C:\Program Files (x86)\Aatrix Software C:\ProgramData\Aatrix Software C:\%LocalAppData%\Sage\Sage 100 Contractor Network location of Sage 100 Contractor data

Report scheduling and faxing functionality

About setting up emailing and faxing through Sage 100 Contractor

Using the faxing functionality through the Sage 100 Contractor program requires:

- Installation of the Windows operating system Fax Service component
- A separate installation and setup of a fax modem in your workstation
- Access to an analog phone line.

In addition, you will also have to set up the cover page information and the number of times that the fax re-tries to send.

For more information about installing and setting up your fax modem, refer to the documentation that came with your fax modem. Sage 100 Contractor does not provide support for installing or setting up a fax modem.

For more information about installing the Windows operating system Fax Service component, see [Installing the Window Fax Services component](#).

Upgrade to the latest version of Adobe Reader

Adobe Reader supports faxing from Windows. To fax from Sage 100 Contractor, you should download and install the latest version from <http://get.adobe.com/reader/>.

Disable automatic updating for Adobe Reader

If you are using the scheduling capability for sending faxes, we recommend that you disable the automatic “check for updates” capability of Acrobat Reader as it will prevent scheduled reports from completing.



NOTE: Instructions for disabling automatic “check for updates” differ from version to version of Adobe Reader. Refer to the Adobe Reader Help for instructions.

Report Scheduling and Email Functionality



IMPORTANT: Using the email capability of Sage 100 Contractor requires Microsoft Outlook or access to a simple mail transfer protocol (SMTP) email server.

The **Email Settings** window provides a way for you to set up email. You can change the selections to accommodate different emailing preferences.

You can access the **Email Settings** window through:

- Any **Report Printing** window by clicking the **Email** button on the toolbar to open the **Email Distribution** windows. Then, click the **Email Settings** button to open the **Email Settings** window.
- **7-9 Alerts Manager**
- Click on **Settings** in the Dispatch Board, then click on **Email Setup**.

Sage 100 Contractor and SMTP



IMPORTANT: The SMTP server may be located on your workstation PC, on a server on your company’s network, or at your Internet service provider (ISP). If the email server is local, you may need the assistance of an IT professional to properly identify or set up this capability. If the email server is located at your ISP, you may need contact your ISP for assistance.

Using the ISP’s simple mail transfer protocol (SMTP) server to send email via Sage 100 Contractor typically requires “user authentication” at the SMTP server. An example of an SMTP email server name is smtp.att.sbcglobal.net.

Different ISPs may use different terms when referring to user authentication. In general, however, user authentication means verifying a user’s identity by means of a “user name” and “password.”

In the context of sending email through Sage 100 Contractor using an ISP’s SMTP server, user authentication only refers to verifying the user’s identity at the ISP’s SMTP server. It does not refer to your:

- Sage 100 Contractor user name and password
- Network domain user name and password
- Windows system user name and password.



NOTE: We do not provide support for setting up or installing an email server. You set up user authentication and your fax line access dial out number on **7-2 Company Information**.

Installing the Windows Fax Services component

To fax from Sage 100 Contractor, you must install the Windows Fax Services component:

Vista:

1. Click **Start > Control Panel > Programs > Turn Windows features on or off**.
2. On the **Windows Features** window, locate the **Windows fax and scan** check box, then select it.
3. Click **[OK]**.

Windows 7:

1. Click **Start > Control Panel > Programs > Turn Windows features on or off**.
2. On the **Windows Features** window, locate **Print and Document Services**, then click the **Windows fax and scan** check box.
3. Click **[OK]**.

Windows 8:

1. Click **Start > All apps > Control Panel > Programs > Turn Windows features on or off**.
2. On the **Windows Features** window, locate **Print and Document Services**, then click the **Windows fax and scan** check box.
3. Click **[OK]**.

Windows Server 2012

[Detailed information from Microsoft](#)

Chapter 3: Sage 100 Contractor Installation

This chapter provides detailed information and instructions for installing Sage 100 Contractor software in different environments, such as:

- Single user
- Peer-to-peer
- Network

Installation preview

Pre-installation information for new customers

Implementing and running your business in Sage 100 Contractor must be thoroughly planned out in advance to harness the power of this software. Your existing company data must be migrated before you start working in the program. Your business partner can assist you with a data migration and business implementation plan. For more information about implementing Sage 100 Contractor for your company, see the information about [business partners](#) in Chapter 1 of this guide.

We recommend that you take full advantage of all the knowledge and advice found in Sage 100 Contractor documentation and training classes. We also recommend that you work with your business partner and accounting professionals before you begin to implement this software for your business.



IMPORTANT: We recommend that you install the Sage license server on a computer that is always available to other computers on your network that are running Sage 100 Contractor.

Pre-installation information for existing customers

Because existing customers are working with company information and possibly with scheduled reports, review these important points before you install the program.



NOTE: Before you install, make at least one backup copy, but consider making two backup copies of your existing company data for an extra margin of safety.

Upgrade Paths

Upgrade From	Upgrade Path
18.x	Upgrade directly to version 19.x
17.x	Upgrade to 18.x, reindex your data, and then upgrade to 19.x

Upgrade From	Upgrade Path
16.x	Upgrade to 18.x, reindex your data, and then upgrade to 19.x
15.x	Upgrade to 18.x, reindex your data, and then upgrade to 19.x
14.x	Upgrade to 18.x, reindex your data, and then upgrade to 19.x
13.x	Upgrade to 14.x, reindex your data, and then upgrade to 19.x
12.x	Upgrade to 13.x, reindex your data, and then upgrade to 19.x
11.x	Upgrade to 13.x, reindex your data, and then upgrade to 19.x
10.x	Upgrade to 13.x, reindex your data, and then upgrade to 19.x

Duration of the installation process

Plan on at least five and possibly up to 20 minutes per computer to install Sage 100 Contractor. The duration of the Sage 100 Contractor installation depends a great deal upon each computer's configuration. For example, some newer computers are pre-installed with essential software required to run Sage 100 Contractor software such as the .NET Framework 3.5 Service Pack 1. Installation to older computers may take more time.

Additional required software

Microsoft .NET Framework 4.0 must be installed on all computers running Sage 100 Contractor software. The installer determines if the .NET Framework 4.0 is already installed. If not, the installer installs the required software automatically.


Plan for an additional 20 minutes per computer to install .NET Framework 4.0.



NOTE: It is very important that you understand the network environments and operating systems on the computers and server computers where you install Sage 100 Contractor software. For detailed information about installing to different environments, see [Special Configurations—Operating Systems and Services](#).

About installing the Sage 100 Contractor software to different configurations

You can install Sage 100 Contractor software to many different configurations, for example, stand-alone, network server, Citrix and Terminal Services servers, peer-to-peer, and workstations.

 **IMPORTANT:** The optimal operational size of a peer-to-peer network running Sage 100 Contractor is two to five workstations. Additional workstations may adversely impact Sage 100 Contractor response times. Networks consisting of more than five (5) workstations may need to use one computer as a dedicated server.

Sage 100 Contractor allows users to share data and reports stored on a network hard drive. From different workstations, users can then access the server to share one set of data, one set of reports, and one set of report forms.

During installation, the installer checks for the components necessary to run Sage 100 Contractor and then copies the program modules and standard reports to the **Programs (x86)** folder and subfolders on the hard disk. In addition, the installation process copies system files necessary for program operations to the Windows and Windows System folders.

The installation process does not make any configuration changes to the computer. After installation is complete, you must configure the stand-alone computer, server computer, or workstation for optimal performance.

For detailed information about configuring each server and workstation depending on its operating system, see [Chapter 8 Special Configurations—Operating Systems and Services](#).

Connectivity across your network

For client workstations to be able to run Sage 100 Contractor, they must all be connected to the Sage license server. If one user sees the “Sage 100 Contractor can’t communicate with the designated Sage license server” message when all other people are connected, then you know that the connectivity problem is limited to that one person. If you encounter a hardware failure with your license server, then no one will be able to run Sage 100 Contractor.

Mapping a network drive to access a company

You may have to map to a network drive to access a Sage 100 Contractor company if it is not located on a drive on your local computer. Let’s suppose that the company has been moved to network drive Z: Now to access the company data, you have to map to drive Z.

To map a network drive to access a company:

1. On your Windows desktop, click **Start > Explore**.
2. On the toolbar, click **Tools > Map Network Drive**.
3. On the Map Network Drive window, click **[Browse]**.
4. Locate the drive, and then click **[OK]**.
5. On the Map Network Drive window, click **[Finish]**.
6. On the Company List window, select drive **Z**.
7. Select the company, and then click **[OK]**.

Installing the Sample Company

The Sample Company provides the means for viewing and working with sample data in Sage 100 Contractor windows. There are sample accounts, sample employees, sample takeoffs, and much more. By viewing and working with this sample data, you can gain an understanding of how different windows interact with the sample data when managing a construction business with Sage 100 Contractor.

Sage 100 Contractor master trainers use the Sample Company extensively during Sage 100 Contractor training classes. We highly recommend that you load the Sample Company during your initial installation.

You can log on to the Sample Company using "Supervisor" as the user name. You do not need a password.

The Sample Company:

- Allows you a safe way to try out new functions as you learn them.
- Is used in many online and recorded classes.
- Provides samples of many Sage 100 Contractor forms that are all filled in. This makes it easy to understand many concepts.
- Provides starter lists for many values you'll need to set up: cost codes, cost types, tasks, client status, client type, employee positions, paygroups, and so on.
- Provides you with live data to investigate the content of Sage 100 Contractor reports.
- Takes very little space on your hard disk drive.

Installing the Sample Company overwrites any previous installations of the Sample Company. If you have made changes in your Sample Company that you want to keep, rename this folder before installing a fresh copy of the Sample Company.

New installations

A new installation is defined as installing the software on a computer that has never had Sage 100 Contractor installed on it before.




NOTE: Instructions for reinstallation/upgrade installation over an existing installation are different. See "Before upgrading" on page 23.

You must designate one computer on your network as the Sage license server. This server will manage use of Sage 100 Contractor (for example, the number of people who can use Sage 100 Contractor simultaneously on your network). You must install the software on this computer first, and then activate your licenses before installing Sage 100 Contractor on your other computers.

Copy the entire set of installation files (all files and folder) to a folder that you create on a network drive. Install the program to each client workstation by launching the installation from the network folder from that client workstation. We recommend that you install to the Sage license server computer first. Then, when you install the program to your workstations, you can set up Sage 100 Contractor to find the Sage license server and run the program using your license.

The installation process also presents different installation windows depending on whether you are installing Sage 100 Contractor as the Sage license server or you are just installing Sage 100 Contractor by itself.

 **IMPORTANT:** Always start installing the program at the computer that will be your Sage license server, which is likely to be your network server.

Basic steps for new installations are:

1. Install the program on your network server, the computer where all your company data is located. You do this only once on your network.

Remember to write down the Sage license server computer's IP Address and/or computer name, which is displayed at the end of the installation.

2. Activate your licenses.
3. Install the program to all client workstations on your network.
4. From each client workstation, specify the Sage license server.

Installing Sage 100 Contractor on the Sage license server

Use these instructions when installing the software on the computer you'll use as the Sage license server or if you are running in a stand-alone environment. Stand-alone means that you are running Sage 100 Contractor on one computer, or you are not networking with other computers running Sage 100 Contractor.

To install from a download package unzipped into a local or shared folder:

1. Close all open programs except for firewall and anti-virus programs.
2. Browse to the drive and folder where you downloaded and extracted the software package.
3. In the folder, locate the setup.exe file, and then double-click it.
4. On the installation option window, select the option **This computer will be my Sage license server**, and then click **[Next]**.
5. On the license agreement window, read the License Agreement carefully.
6. Select the check box to accept the terms, then click **[Next]** to continue the installation.
7. On the select product edition window, specify whether to install the US or Canada edition.
8. On the select additional options window, select the option **Install the Sample Company for training purposes**. We recommend that you install the Sample Company.
9. Click **[Install]**.


NOTE: The installer begins the installation process. It checks to see if the computer has .NET Framework 4.0 installed. If this program is not found, the installer installs it.

At the end of the installation process, a confirmation window appears containing a list of installed programs.

- Sage 100 Contractor
- License Administration for Sage 100 Contractor

This window also displays the computer's IP Address and its network name. You will use this information to specify the Sage license server.

10. Review the list of installed programs, and write down the IP Address and network name of the computer.


 **IMPORTANT:** Write down and keep the Sage license server computer's IP Address and name in a convenient location. To select the Sage license server from client computers running Sage 100 Contractor, you need to select its name from a list or type the computer's IP Address or name in a text box.

11. Click [**Next**].


The activate your product licenses window appears. The **Launch the License Administration program** check box is preselected to launch the License Administration program, so you can activate your licenses.

12. Read the instructions about activating your product licenses, and then click [**Finish**], leaving the **Launch the License Administration program** check box selected.

For information about this process, press **F1** when viewing the main License Administration window.

 **NOTE:** When Sage 100 Contractor is installed, an icon labeled License Administration is placed in the **Start > Programs > Sage 100 Contractor** menu of Windows and a file named Sage.SMB.LicenseAdministration.exe in the **Programs (x86)\Sage\Sage 100 Contractor** folder to provide you with the convenience and ability to view license information or update license information for your provisioned license server while on a machine other than the provisioned license server. You can provision additional licenses you have recently acquired to the actual license server machine without having to be present at the actual license server.

Installing Sage 100 Contractor on client workstations

 **IMPORTANT:** Before installing the software, close all open programs except for firewall and anti-virus programs.

To install Sage 100 Contractor from a download package unzipped into a local or shared folder:

1. Browse to the drive and folder where you downloaded and extracted the software package.
2. In the folder, locate the setup.exe file and double-click it.
3. Read the instructions on the installation welcome window, and click [**Next**].
4. On the installation option window, select the option This computer will run Sage 100 Contractor only, and click [**Next**].
5. On the license agreement window, read the License Agreement carefully.
6. Select the check box to accept the terms, then click [**Next**] to continue the installation.

The installer begins the installation process. It checks to see if the computer has .NET Framework 4.0. If this program is not found, the installer installs it.

7. Install the Sample Company for training purposes.



TIP: We recommend that you install the Sample Company.

An installation complete window appears. The **Launch Sage 100 Contractor** check box is preselected so that you can launch Sage 100 Contractor and specify the Sage license server.

8. Read the important message and follow the instructions to launch Sage 100 Contractor.
9. Click **[Finish]**.
10. Sage 100 Contractor begins its launch process by displaying the Specify Sage License Server window.



NOTE: When Sage 100 Contractor is installed, an icon labeled License Administration is placed in the **Start > Programs > Sage 100 Contractor** menu of Windows and a file named Sage.SMB.LicenseAdministration.exe in the \Program Files (or Program Files (x86))\Sage\Sage 100 Contractor folder to provide you with the convenience and ability to view license information or update license information for your provisioned license server while on a machine other than the provisioned license server. You can provision additional licenses you have recently acquired to the actual license server machine without having to be present at the actual license server.

Upgrade installations

If you currently have Sage 100 Contractor installed on your network computers and you are going to reinstall it, you could be either upgrading or updating the software.

Upgrade installations involve major changes, enhancements, and fixes to many parts of the program or to modules such as licensing. For example, installing Version 19 over Version 18 is an upgrade installation because there are major enhancements to the program.

Update installations, in contrast, usually involve changes to specific files, such as the Sage.SMB.PayrollTax.dll file and report forms. These files can be changed and updated without any changes to major parts of the program.

In addition, upgrade installations are different from new installations. During new installations (or reinstallation after completely removing Sage 100 Contractor and Sage licensing), you can designate a computer to be either the Sage license server or a client workstation.

Before upgrading

Before you upgrade your Sage 100 Contractor software, you need to complete certain preliminary tasks to ensure the safety of your company data.



IMPORTANT: Choose a block of time when you can install the upgrade to all the computers in your office beginning with your Sage license server. Depending on your computer's hardware and your network configuration, plan on 15 minutes per computer for the installation process alone. Additional tasks may take extra time.

Before upgrading Sage 100 Contractor:

1. Back up your company data.

We suggest making two backup copies in case one of them is incomplete, becomes corrupted, or is lost.

2. Exit Sage 100 Contractor and all other programs.



IMPORTANT: You must not install the Sage 100 Contractor upgrade when either Sage 100 Contractor or the Sage 100 Contractor API are running. We recommend that you shut down all other programs when installing Sage 100 Contractor, but you do not have to shut down firewall and anti-virus software.

3. Locate the computer on your network that is your Sage license server, and begin the upgrade installation there.

Upgrade installation

Always begin all installations at the computer that is the Sage license server. After installing the upgrade to the Sage license server, install the upgrade to your workstations from the image placed in a folder on the network. For example, if you want to install Sage 100 Contractor to a network drive, you have to go to that computer and install the program from there.

Sage 100 Contractor running on client workstations needs to connect to the Sage license server to access your company data. If you do not change the designation of any computers on your network during an upgrade installation, all client workstations will be able to locate the existing Sage license server again after installation.

Installing the upgrade

When installing, use the same upgrade installation steps for both your Sage license server and your workstation computers.



IMPORTANT: Install the upgrade to the existing Sage license server computer first. Install the upgrade to all workstations only after the license server installation has been completed.


To install the upgrade from a download package unzipped into a local or shared folder:

1. Shut down Sage 100 Contractor and all open programs except for firewall and antivirus programs.
2. Browse to the drive and folder where you extracted the upgrade files.
3. Before you proceed further with installation, we recommend that you double-click the *ReleaseNotes.pdf* to open it in your PDF viewer.

Review the *Release Notes* for information about enhancements, program fixes, known issues, and other information that might affect your upgrade installation.

4. Double-click Setup.exe to begin the installation.
5. If you get a message asking if you want to allow the following program to make changes to this computer, click **[Yes]**.

6. On the welcome window, notice that a previous installation has been found, and click **[Next]**.
7. On the installation option window, select an option, and click **[Next]**:
 - a. **This computer will be my Sage license server**
 - b. **This computer will run Sage 100 Contractor only**
8. On license agreement window, read the license agreement carefully.
9. Select the check box to accept the terms, and then click **[Next]**.
10. On the select additional options window, select the option to install the Sample Company. We recommend that you install the Sample Company, which is used extensively in Sage 100 Contractor training classes.


 **IMPORTANT:** The upgrade installation overwrites the existing Sample Company. If you want to save changes to the existing Sample Company, clear the check box. If you do not overwrite the Sample Company, you must rebuild the indexes in the Sample Company database using 7-4 Rebuild Indexes after the upgrade installation. If you have made changes in your Sample Company that you want to keep, rename this folder before installing a fresh copy of the Sample Company.

11. Click **[Next]**. The installation proceeds.
12. On the Installation complete window, click **[Finish]** to launch Sage 100 Contractor.
13. Repeat steps 1 through 12 to upgrade all other computers running Sage 100 Contractor.
14. Follow the instructions for post-installation tasks to rebuild the indexes for your company database from one computer, and reschedule your reports, as necessary.

Uninstalling Sage 100 Contractor from a Sage license server

When Sage 100 Contractor is uninstalled from an active license server, the server's licenses are deauthorized and made available to be acquired by another license server. If the Sage license server crashes and the licenses are not deauthorized, contact [Customer Support](#) to have the licenses unlocked.

If uninstalling and then reinstalling to a Sage license server, the licenses need to be [reactivated](#) after reinstallation.

 **NOTE:** Sage 100 Contractor implemented the current License Administration program with Version 18.1. Any version of Sage 100 Contractor earlier than 18.1 is using a different license administration program.

Chapter 4: ACT! Plug-in Installation

This chapter provides information and instructions for installing the ACT! plug-in for use with Sage 100 Contractor.

Pre-installation information

For Sage 100 Contractor to integrate with ACT!, the following requirements must be met:

- Sage 100 Contractor 2013 Version 18.1 or later must be installed
- ACT! Premium or ACT! PRO (version 2011 or later) must be installed
- ACT! plug-in license use must be obtained

Duration of the installation process

Plan on at least five to ten minutes per computer to install the ACT! plug-in. The duration of the Sage 100 Contractor installation depends a great deal upon each computer's configuration. Installation to older computers may take more time.

Additional required software

ACT! Premium or ACT! PRO (version 2011 or later) must be installed on all computers running Sage 100 Contractor software that use the ACT! plug-in.

Plan for an additional 10 to 15 minutes per computer to install ACT! Premium or ACT! PRO.



NOTE: It is very important that you understand the network environments and operating systems on the computers and server computers where you install Sage 100 Contractor software. Chapter 6 Special Configurations provides detailed information about installing to different environments.

Installing the ACT! Plug-in

Basic steps for installation are:

1. Verify Sage 100 Contractor and ACT! Premium or ACT! Pro (version 2011 and later) are already installed.
2. Activate your ACT! plug-in license.
3. Install the ACT! plug-in on any client workstations where you use ACT!.

Installation of Sage 100 Contractor and ACT!

To install Sage 100 Contractor, refer to “Chapter 3: Sage 100 Contractor Installation” in this guide.

To install ACT!, refer to the installation instructions that came with ACT! Premium or ACT! PRO (version 2011 or later) and see the ACT! Getting Started Resource Center at <http://na.sage.com/Sage-ACT/support/Getting-Started>.

Activate your ACT! plug-in license use

To activate your ACT! plug-in license, refer to “Chapter 6: Managing Your License” in this guide.

To install the ACT! plug-in on client workstations:

1. Close all open programs except for firewall and antivirus programs.
2. Browse to the drive containing Sage 100 Contractor (for example, **Programs (x86) > Sage > Sage 100 Contractor**).
3. Double-click **ACTPluginSetup.exe** to begin the installation.
4. On the welcome window, click **[Next]**.
5. On the Installation complete window, click **[Finish]**.
6. Restart your computer as necessary.

Chapter 5: Sage Construction Anywhere Installation

This chapter provides information about setting up Sage 100 Contractor for use with Sage Construction Anywhere.

Additional required software

- The Sage Construction Anywhere Connector should be installed on at least one computer running Sage 100 Contractor software that connect to Sage Construction Anywhere, but can also be installed to a separate server. The Sage Construction Anywhere Connector connects your back office software to your Sage Construction Anywhere site. The connector installation includes the Sage Construction Anywhere Connector software and its required prerequisite software.
- An Internet connection using a compatible web browser. See "Appendix A: System Requirements" for supported browsers in the Getting Started Guide at .



NOTE: A static Internet connection using a compatible web browser is required for Sage Construction Anywhere.

For current information on supported browsers, supported Sage 100 Contractor versions, and other system requirements, see the Sage Construction Anywhere help at http://help.sageconstructionanywhere.com/sage100contractor/help/Default.htm#01_Setup/System_requirements.htm.

Duration of the installation process

Plan on at least five to ten minutes per computer to install the Sage Construction Anywhere Connector software. The duration of the Sage 100 Contractor installation depends a great deal upon each computer's configuration. Installation to older computers may take more time.

Pre-installation information

To integrate Sage 100 Contractor with Sage Construction Anywhere, you must install and set up supported versions of the following programs:

- Sage 100 Contractor
- Sage Construction Anywhere

For current information on supported browsers, supported Sage 100 Contractor versions, and other system requirements, see the Sage Construction Anywhere help at http://help.sageconstructionanywhere.com/sage100contractor/help/Default.htm#01_Setup/System_requirements.htm.



NOTE: A static Internet connection using a compatible web browser is required for Sage Construction Anywhere..

Setting up Sage Construction Anywhere Integration

In order for Sage 100 Contractor to integrate with Sage Construction Anywhere, the following programs must be installed and set up:

- Sage 100 Contractor 2013 Version 18.3 or later must be installed
- Supported version of Sage Construction Anywhere

In addition, an API user needs to be set up for any companies that are to be integrated.

- In Sage 100 Contractor, in **7-3-1 Security Groups**, an API security group must exist with the appropriate save permissions. See "Setting up an API security group and an API user in Sage 100 Contractor" below to set up the API group.
- In Sage 100 Contractor, in **7-3-2 User List**, a user that is a member of the API group must be set up.

Setting up an API security group and an API user in Sage 100 Contractor

Security groups let you control users' ability to open windows as well as perform specific actions within a window. The **7-3-1 Security Groups** window in Sage 100 Contractor contains a grid with numbered rows on the left and eight columns:

- Group# (User input is required to save the record.)
- Group Name (User input is required to save the record.)
- Save
- Delete
- Void
- Chg Period
- Print Checks
- Notes

When you set up user groups, you type a group number and group name. Then you determine whether or not that group will have rights to **Save**, **Delete**, and **Void** records, as well as to change the accounting period and print checks. You may use the Notes column to add any pertinent information about each group.

You must create an API security group that is named exactly **API**. At least one user must be added to the API security group. You have to set rights to save, void, and so on.



IMPORTANT: If you use security groups for the tasks performed by the employee in Sage 100 Contractor, make sure the Sage Construction Anywhere user has access to all areas of Sage 100 Contractor.

To set up a security group for using the API

1. Open **7-3-1 Security Groups**.
2. In the **Group#** cell, type a group number, such as **51**.
3. In the **Group Name** cell, type **API** and do the following:

 **IMPORTANT:** The API security group must be named exactly **API**.

- a. In the **Save, Delete, Void, Chg Period, and Print Checks** cells, type **Yes**.
 - b. To store information that may be relevant or important to that specific group, type a note in the **Notes** cell.
4. On the **File** menu, click **Save**.



TIPS:

- Before you can use the API security group to access Sage 100 Contractor company data, you have to assign a user to the API security group.
- Security is set up for each individual company, not for the entire program. Each company can use different user names and passwords. If you have more than one company, you have to set up passwords for multiple companies.

Then you have to assign a user to the API security group using **7-3-2 User List**.

The **7-3-2 User List** window controls major features dealing with users and program security.



NOTE: The user name and password created are for administrative use only. This information is for use by the Sage Construction Anywhere Connector program only, and is not needed by the individual employee(s) using Sage Construction Anywhere.

To assign a new user to the API security group

1. Open **7-3-2 User List**.
2. In the **User Name** cell, enter a user name, such as **SCAUser**.
3. In the **Password** cell, enter a password.
4. In the **Group 1** cell, click once in the cell, and from the drop-down list, select the **API** group.
5. Click **File > Save**.



IMPORTANT: The API will not accept “supervisor” as a user name.

To assign an existing user to the API security group

1. Open **7-3-2 User List**.
2. Find the **User Name** for the person who will use Sage Construction Anywhere.
3. In the **Group 1, Group 2, Group 3, Group 4, or Group 5** cell, click once in the cell, and from the drop-down list, select the **API** group.

4. Click **File > Save**.

Chapter 6: Managing Your License

This chapter provides detailed information about:

- Managing and activating your license
- Using License Administration

License administration

When you purchase Sage 100 Contractor software, it includes the License Administration program. Using the License Administration program, you can activate licenses and monitor the license uses. During software installation, the License Administration program is automatically installed on the computer that the software installer designates as the Sage license server.



IMPORTANT: Before you can use Sage 100 Contractor with your activated license, you have to specify the computer on your network that is the Sage license server when you launch Sage 100 Contractor.

Where is the Sage license server located?

The Sage license server is software running on a computer on your network that manages the Sage 100 Contractor products and features that you purchased. Products and features can be a “core product,” additional “modules,” and a number of “license uses.” The computers running your Sage 100 Contractor have to be connected to the computer running the Sage license server so that the correct products, features, and number of license uses are available to you.

Which versions of Sage 100 Contractor use License Administration?

Sage 100 Contractor implemented the current License Administration program with Version 18.1. Any version of Sage 100 Contractor earlier than 18.1 will not work with the License Administration program described in this chapter.

About managing licenses

Use the License Administration window to activate licenses and monitor license uses.

Activating licenses

In order to use Sage 100 Contractor, you have to activate your product licenses.

To activate your license:

1. On the License Administration window, click the **Edit registration info** link.
2. Enter your **Sage client ID**.
3. Enter your **Registration name**.
4. Click [**OK**].

Chapter 7: License Use and Sage 100 Contractor

This chapter provides all the necessary details about:

- Specifying the Sage license server
- Managing license attributes
- Understanding license uses

Specify Sage License Server

What is a server?

There are many kinds of servers. Some servers are denoted by their hardware configuration and a specialized operating system. Other servers consist of specialized software applications running on standard computers.

Some servers are called “file servers” and may be a powerful computer dedicated to storing files and data. For example, Sage 100 Contractor company data can be stored on a file server. Any Sage 100 Contractor user on the same network as the file server can access and store data there.

A server can also be a software application that provides a specific kind of service to client software running on other computers. The term server can refer to a particular piece of software, such as the Sage license server. When we refer to the Sage license server, we are describing a computer that is running the Sage license server software.

Before you can use Sage 100 Contractor with your activated license, you have to specify the computer on your network that is the Sage license server. There are two ways to specify the Sage license server:

- You can select the computer from the list of computers on your network; or
- You can enter the IP Address or name of the computer.

Selecting the Sage license server computer

One method is to select the computer running the Sage license server from the list of network computers.



NOTE: To use this method of selecting a server from the list of network computers, you must have already clicked the appropriate link on the Specify Sage License Server window.

To select the computer running Sage license server from the list of network computers:

1. On the Select License Server window from the list of network computers, select the computer running the Sage license server.
2. Click **[OK]**.

Entering the IP Address or name of the computer

One method is to enter the IP Address or name of the computer running the Sage license server.

To enter the IP Address or name of the computer running the Sage license server:

1. In the text box, type the IP Address or name of the computer.
2. Click **[OK]**.

Determining the IP Address of a computer



NOTE: If you are trying to determine the IP Address computer running the Sage license server, you must complete this procedure on that computer.

To determine the IP Address of a computer:

1. Click **Start > Run**.
2. In the Open text box, type `cmd`, and then click **[OK]**.
The `\Windows\...\cmd.exe` window appears.
3. At the prompt, type `ipconfig`.
For example, you might see `H:\.`. Type `ipconfig` after the drive letter.
4. Press the **[Enter]** key.

The system displays several addresses including the IP Address of the computer, similar to this line:

```
IP Address . . . . . .172.20.22.142
```

What is an IP Address?

Every computer connected to the Internet is assigned a unique number known as an Internet Protocol (IP) address. This numeric address of a computer on the Internet is written as a set of four numbers separated by periods (each number can range from 0 to 255). An example of an IP Address is 123.123.4.5.

Determining the name of a computer



NOTE: If you are trying to determine the name of the computer running the license server, you must complete this procedure on that computer.

To determine the name of a computer:

1. On your Windows desktop, click **Start > Settings > Control Panel**.
2. From the list, scroll to and then double-click **System**.
The **System Properties** window appears.
3. Locate the line **Full computer name**, and then make a note of the name.
4. Click **[Cancel]**.

Chapter 8: Special Configurations— Operating Systems and Services

This chapter contains information about special configurations for specific operating systems, such as:

- Windows 8 Professional and Server 2012 Standard
- Windows® 7 Professional and Windows Server 2008® R2 Standard
- Windows Vista® and Windows Server 2008
- Citrix® and Terminal Servers

Windows 8 Professional and Server 2012 Standard Operating Systems

Windows 8 Professional and Server 2012 Standard "Sleep Mode" prevents computers from obtaining a license use

If a computer running the Windows 8 Professional or Server 2012 Standard operating system is used as a license server, when it goes into sleep mode other computers on the network can't obtain a license.

To avoid this possibility, set **Sleep Mode** on your license server computer to **Never**.

To set the Sleep Mode to "Never":

1. **Start > All apps > Control Panel > System and Security > Power Options.**
2. Select **Change when computer sleeps.**
3. From the **Put computer to sleep** list, select **Never.**

Sage licensing (Sage 100 Contractor Hosting Framework) cannot auto-start on Windows 8

The Sage licensing service (Sage 100 Contractor Hosting Framework) cannot auto-start on computers running the Windows 8 Professional or Windows 8 Enterprise operating systems. If the service stops, the program displays a message advising you to take further action to resolve this issue.

Solution for Server 2012 error message about mb7.kpr file

If you encounter an error message about opening the mb7.kpr file when launching Sage 100 Contractor on a computer running Windows Server 2012, follow these steps to resolve the issue:

1. On the Windows desktop, right-click **Start**, and then click **Explore.**
2. On the left side of the window, under **Folders**, right-click the MB7 folder, and then select **Properties.**
3. On the **MB7 Properties** window, click the **Security** tab.

4. From the list under **Group or User Names**, select **USERS**, and then click [**Edit**].
5. On the **Permissions** window, select **USERS** again, and under **Allow**, select the **Full control** check box.
(Selecting **Full control** selects all the check boxes necessary for this solution.)
6. On the **Permissions** window, click [**OK**].
7. On the **MB7 Properties** window, click [**OK**].

Server 2012 network configuration and TCP Remoting Channel

Sage 100 Contractor uses the TCP Remoting Channel, a Microsoft .NET Framework component to enable communication among computers on a network. File and printer sharing on computers running the Server 2012 operating system must be enabled. To enable file sharing, follow the instructions in the Windows Server 2012 Help.

Windows 7 Professional and Server 2008 R2 Standard Operating Systems

Windows 7 Professional, Windows 8 Professional, and Server 2008 R2 Standard "Sleep Mode" prevents computers from obtaining a license use

If a computer running the Windows 7 Professional, Windows 8, or Server 2008 R2 Standard operating system is used as a license server, when it goes into sleep mode, other computers on the network can't obtain a license.

Set **Sleep Mode** on your license server computer to **Never**.

To set the Sleep Mode to "Never":

1. **Start > Control Panel > System and Security > Power Options**.
2. Select **Change when computer sleeps**.
3. From the **Put computer to sleep** list, select **Never**.

Sage licensing (Sage 100 Contractor Hosting Framework) cannot auto-start on Windows 7 Professional and Server 2008 R2 Standard

The Sage licensing service (Sage 100 Contractor Hosting Framework) cannot auto-start on computers running the Windows 7 Professional or Server 2008 R2 Standard operating systems. If the service stops, the program displays a message advising you to take further action to resolve this issue.

Solution for Server 2008 R2 error message about mb7.kpr file

If you encounter an error message about opening the mb7.kpr file when launching Sage 100 Contractor on a computer running Windows Server 2008 R2, follow these steps to resolve the issue:

1. On the Windows desktop, right-click **Start**, and then click **Open Windows Explorer**.
2. On the left side of the window, under **Computer > Local Disk**, right-click the **MB7** folder, and then select **Properties**.
3. On the **MB7 Properties** window, click the **Security** tab.
4. From the list under **Group or User Names**, select **USERS**, then click the **[Edit]** button.
5. On the **Permissions** window, select **USERS** again, and under **Allow**, select the **Full control** check box.
Selecting **Full control**, selects all the check boxes necessary for this solution.
6. On the **Permissions** window, click **[OK]**, and then on the **MB7 Properties** window, click **[OK]**.

Server 2008 R2 network configuration and TCP Remoting Channel

Sage 100 Contractor uses the TCP Remoting Channel, a Microsoft .NET Framework component to enable communication among computers on a network. File and printer sharing on computers running the Server 2008 R2 operating system must be enabled. To enable file sharing, follow the instructions in the Windows Server 2008 R2 Help.

Windows Server 2008 R2 and Microsoft .NET 3.5.1

Microsoft .NET 3.5.1 must be available and enabled prior to installing Sage 100 Contractor on a Windows Server 2008 R2 machine. Server 2008 R2 comes with .NET 3.5.1 loaded but not installed, so Sage 100 Contractor doesn't install it automatically.

If you attempt to install Sage 100 Contractor without .NET 3.5.1 installed, you will receive the following message during the licensing install: "Sage.CRE.HostingFramework.Service v3.2 has stopped working." When you click **[OK]**, the installation continues, but the services have not been installed so Sage 100 Contractor cannot open. The Sage.CRE.HostingFramework Service will not install unless .NET 3.5.1 has been installed. If you receive the above message during installation, install .NET Framework 3.5.1 and reinstall Sage 100 Contractor.

To verify that .NET 3.5.1 is installed on Windows Server 2008 R2:

1. Click the **Start** button in the lower left corner of the display.
2. Highlight **Administrative Tools** and select **Server Manager**.
3. In the **Server Manager** interface, click **Features** to display all the installed Features in the right-hand pane. Verify that .NET Framework 3.5.1 is listed.

To enable .NET 3.5.1 on Windows Server 2008 R2:

1. In the **Server Manager** interface, select **Add Features** to display a list of possible features.
2. In the **Select Features** interface, expand **.NET Framework 3.5.1 Features**.
3. Once you expand **.NET Framework 3.5.1 Features**, you will see two check boxes. Check the box next to .NET Framework 3.5.1 and click **Next**.

4. In the **Confirm Installation Selections** interface, review the selections and then click [**Install**].
5. Allow the installation process to complete and then click [**Close**].



NOTE: Enabling .NET Framework 3.5.1 may require a reboot.

Windows Vista and Server 2008 Operating Systems

Vista and Server 2008 “Sleep Mode” prevents computers from obtaining a license use

If you are using a Vista or Server 2008 computer as the Sage license server and it goes into **Sleep Mode**, the workstations cannot obtain a license use.

Use a different computer on your network to be the Sage license server. Any supported operating system can be used in place of Vista or Server 2008.

Set **Sleep Mode** on your license server computer to **Never**.

To set the Sleep Mode to "Never":

1. **Start > Control Panel > System and Maintenance > Power Options.**
2. Select **Change when computer sleeps.**
3. From the **Put computer to sleep** list, select **Never.**

Sage licensing (Sage 100 Contractor Hosting Framework) cannot auto-start on Vista, Windows 7, Windows 8, or Server 2008



IMPORTANT: Read this information if you are running Vista or Server 2008 operating systems on your office computers.

The Sage licensing service (Sage 100 Contractor Hosting Framework) cannot auto-start on computers running the Vista, Windows 7, Windows 8, or Server 2008 operating systems. If the service stops, the program displays a message advising you to take further action to resolve this issue.

Solution for Server 2008 error message about mb7.kpr file

If you encounter an error message about opening the mb7.kpr file when launching Sage 100 Contractor on a computer running Windows Server 2008, follow these steps to resolve the issue:

1. On the Window desktop, right-click **Start**, and then click **Explore.**
2. On the left side of the window, under **Folders**, right-click the **MB7** folder, and then select **Properties.**
3. On the **MB7 Properties** window, click the **Security** tab.
4. From the list under **Group or User Names**, select **USERS**, then click [**Edit**].
5. On the **Permissions** window, select **USERS** again, and under Allow, select the **Full control** check box.

Selecting **Full control** selects all the check boxes necessary for this solution.

6. On the **Permissions** window, click [**OK**], and then on the **MB7 Properties** window, click [**OK**].

Vista, Windows 7, and Server 2008 network configuration and TCP Remoting Channel

Sage 100 Contractor uses the TCP Remoting Channel, a Microsoft .NET Framework component to enable communication among computers on a network. File sharing on computers running the Vista, Windows 7, or Server 2008 operating system must be enabled. To enable file sharing, follow the instructions in the Vista, Windows 7, or Server 2008 Help.

Vista, Windows 7, and Server 2008 and changing the Sage License Server computer

On a Vista, Windows 7, or Server 2008 workstation, when you select **File > Change Sage License Server > Select the computer from the list of computers on your network**, the command may fail to generate a list of network computer names. To resolve this issue, click **Enter the IP address or name of the computer**, and then type the IP address of the server computer in the box.

Citrix and Terminal Servers

Using Citrix and Terminal Server with Sage 100 Contractor

Many people use Citrix and Terminal Server to manage remote access to their local area network (LAN). If Sage 100 Contractor is installed on the computer running Citrix or Terminal Server and on your laptop, then you may log on to the computer running Citrix or Terminal Server with your laptop and work in Sage 100 Contractor on your LAN. This enables you to work from home, from a job site, or from any number of other remote locations.


We recommend that you use DOS commands to change the operating mode from “execute” to “install” and then back to “execute.” When using the DOS commands to install, you may install the Sage 100 Contractor software as you would on any desktop or Windows server operating system that meets Sage 100 Contractor requirements.

Installing on computers running Citrix and Terminal Server using DOS commands

To install using DOS commands:


1. Click [**Start**] > **Run**.
2. On the **Run** window:
 - a. In the **Open** drop-down box, type `cmd`.
 - b. Press [**Enter**].The **\Windows\...\cmd.exe** window appears.

3. When prompted, type `change user /install`, and then press **[Enter]** to turn on the Install mode.
4. Install Sage 100 Contractor as you would on a typical workstation or Windows Server.
5. At the end of the installation process, launch **License Administration Tool**.
6. Use the License Administration Tool window to activate and manage your license.
7. After activation, click **Start > Run**.
8. On the Run window, in the Open drop-down box, type `cmd`, and then press **[Enter]**.
The `\Windows\...\cmd.exe` window appears.
9. When prompted, type `change user /execute` to turn on the Execute mode, the default mode for running Citrix and Terminal Server.
10. Exit the **Run** window.
11. Restart the server.


 **IMPORTANT:** If this message appears: “Install mode does not apply to a terminal server configured for remote administration,” then it is not necessary to enable the install mode. You may install the Sage 100 Contractor software as you would on a typical workstation.

Backing Up Your Data

With any computer system, there is the possibility for failure and loss of data.

 **CAUTION:** Use a backup method and device suitable for your business requirements. We strongly recommend that you maintain a routine backup schedule and store your data in a safe environment that is separate from your server, preferably off site.

Which files to back up in Sage 100 Contractor

 **NOTE:** This topic applies only to existing Sage 100 Contractor customers.


When you back up your company data, we recommend that you back up your company financial data as well as all your custom reports and forms. If you are running multiple Sage 100 Contractor companies, back all of them up.

When backing up data as part of the year-end close process, it is important to count the number of files and folders in your company.

To see the number of files and folder in a company folder, in Windows Explorer, right-click the company folder and select Properties. On the Properties window, the General tab, look in the list for the Contains line for the number of files and folders. Write this number down so that you can refer to it after you have made the two copies. The number of files and folders has to be exactly the same in both the company and the backup copy.

We strongly recommend that you back up:

- Each company folder that contains financial data (\MB7\Your Company\)
- The **Sage 100 Contractor** folder (\Users\Username\AppData\Local\Sage\Sage 100 Contractor)
- The **Report Forms** folder (\MB7\Report Forms)
- The **Custom Reports** folder (\MB7\Custom Reports)

 **IMPORTANT:** When backing up your data, be sure to make a full backup and not an incremental or differential backup. An incremental or differential backup only records alterations to the data since the last backup.

An example of one backup method

There are various methods for backing up your data. Depending on the amount of data you enter routinely, consider making full daily backup copies. It is also a good idea to regularly take one copy off the business premises or store your backed-up data in a fireproof safe. If a burglary or fire occurs, a copy of your data is safe from harm.

One reliable procedure, requiring a tape drive and multiple sets of tapes, requires you to back up your data daily and monthly.

Daily Backup Process

For the daily backup process, you need 10 tapes. Label five of the tapes as Week A, with a tape designated for each weekday. Label the other five tapes as Week B, with a tape designated for each weekday.

Start with the set of tapes labeled Week A. Monday night when you make the backup use the tape labeled Monday, on Tuesday use the tape labeled Tuesday, and so forth. At the start of the next week, use the set of tapes labeled Week B to make your backup copies. At the end of two weeks, you will have backed-up data for each day. Then at the start of the third week, use the set of tapes labeled Week A again. Over the course of a year, you will cycle through the two sets of tapes. Be sure to store the most recent Friday backup off site.

Monthly Backup Process


For the monthly backup process, you need a separate set of three tapes labeled Month A, Month B, and Month C respectively. Like the weekly backups, use each tape to back up the data for a different month, cycling through each of the tapes over the course of the year. After making a monthly backup copy, write the month and year on the label to help you track which tape to use next. Be sure to remove the most recent monthly backup off site.

Backing up your data to a CD or DVD

This topic suggests a generic way to back up your data to a CD or DVD. Backing up to a CD or DVD successfully depends on your computer system, including hardware and software. To back up to a CD or DVD, you must have access to a CD or DVD (Read/ Write capability), and the appropriate CD or DVD media.

When backing up data as part of the year-end close process, it is important to count the number of files and folders in your company. To see the number of files and folder in a company folder, in Windows Explorer, right-click the company folder and select Properties. On the Properties window, the General tab, look in the list for the Contains line for the number of files and folders. Write this number down so that you can refer to it after

you have made the two copies. The number of files and folders have to be exactly the same in both the company and the backup copy.

 **IMPORTANT:** If you are working across a network, you must remember to backup company folders, report folders, and form folders that reside at the server.

To back up your data to a CD or DVD

1. Place the CD or DVD media in the CD or DVD.
2. On your Windows desktop, right-click [**Start**] > **Explore**.
3. In Windows Explorer:
 - a. Locate and then right-click the \Users\Username\AppData\Local\Sage\Sage 100 Contractor folder.
 - b. From the menu, select **Copy**.
4. Locate and then click the CD or DVD drive.
5. In the right-pane, right-click and then select [**Paste**].
6. In Windows Explorer:
 - a. Locate and then right-click the \MB7\ folder.
 - b. From the menu, select **Copy**.
7. Locate and then click the CD or DVD drive.
8. In the right-pane, right-click and select [**Paste**].

Depending on your hardware and software, the folder will be copied to the CD or DVD media. For further information or support, contact your CD or DVD manufacturer.

Configuring Windows Regional and Short Date Format

To specify regional formats for Windows:

1. Click the [**Start**] button, point to **Control Panel**, then click **Clock, Language, and Region** .
2. Click **Region and Language**.
3. On the **Formats** tab, select the format for your country.
4. Under **Date and time formats**, from the Short date format drop-down list, select the format used for your country.
5. Click [**OK**].
6. Close the **Clock, Language, and Region** window.

Index

A

- ACT!
 - installing the plug-in on workstations 27
- autostart
 - Windows 7/Server 2008 R2 37-38

B

- backup 17, 42-43
 - backing up to CD or DVD 43
 - daily backup process 43
 - methods 43
 - monthly backup process 43
 - which files to backup 42

C

- Citrix servers 41
 - DOS cmd installation 41
- communication ports
 - configure 8
- company 19
 - mapping a network drive to access 19
- computer name 36
 - determine 36
 - entering the computer name 36
- customer support
 - knowledgebase 2

D

- date format 44
- document conventions 1
- DOS cmd installation
 - Citrix servers 41
 - Terminal servers 41

F

- fax service component
 - Windows 15
- firewall
 - configure 8
- folder
 - MB7 43
 - Report Forms 43
- forms
 - check 5
 - tax 5

H

- Help 5

I

- install 17-18, 20, 22, 27, 29
 - duration 18, 27, 29
 - installing on client workstations 22
 - installing the Sample Company 20
 - pre-installation for existing customers 17

- pre-installation for new customers 17
- installing
 - ACT plug-in on client workstations 27
- integration
 - Sage Construction Anywhere 30
- Ip Address
 - what is an IPAddress 36
- IP Address 36
 - determining the IPAddress 36
 - entering the IPAddress 36

L

- language 44
- License Administration 33
- license server 33
 - change server computer 41
- licenses 33
 - activating licenses 33
- licensing
 - TCP Remoting Channel 7

M

- methods 43
 - backup 43

N

- network 19
 - connectivity 19

- network configuration
 - licensing 7
- network drive 19
 - mapping network drive 19

O

- operating system
 - fax service component 15
- Outlook 14

P

- port numbers
 - TCP Remoting Channel 8

R

- reports
 - faxing and emailing
 - setup 13

S

- Sage 100 Contractor Hosting Framework 40
 - autostart 37-38, 40
- Sage Construction Anywhere 30
 - setting up integration 30
 - setting up the API security group 30
 - setting up the API user and password 30
- Sage CRE
 - cheques 5
 - forms 5

Sage license server 21, 33, 35

installing the Sage license server 21

managing licenses 33

name 36

selecting server computer 35

Sample Company 20

installing 20

server 35

Server 2008

change license server 41

sleep mode 40

TCP Remoting Channel 7

Server 2008 R2

sleep mode 37-38

TCP Remoting Channel 39

Server 2012

TCP Remoting Channel 38

simple mail transfer protocol 14

sleep mode

Server 2008 40

Server 2008 R2 37-38

Vista 40

Windows 7 37-38

SMTP 14

software 18, 27, 29

additional required software 18, 27, 29

special configuration

Windows 7/Server 2008 R2

autostart 37-38

system configuration

language and date 44

T

TCP Remoting Channel

licensing 7

port numbers 8

Terminal servers 41

DOS cmd installation 41

The Users Group (TUG) 5

training 4

getting started 4

TUG (The Users Group) 5

U

upgrade 24

installing the upgrade 24

V

Vista

change license server 41

sleep mode 40

TCP Remoting Channel 7

W

Windows

fax service component 15

regional and short date format 44

Windows 7

sleep mode 37-38